


Command Center – Adding extra space

1. Choosing the customer



The screenshot shows the Nexetic Command Center interface. At the top left is the Nexetic logo. To its right are navigation links for 'Monitoring' and 'Licenses', with the latter circled in red and marked with a red arrow and the number '1'. Below the navigation is a 'Filter view by' section with a dropdown menu set to 'Vendor' and 'timon tehdas'. Further down is a 'Choose existing:' dropdown menu set to 'NexeTest (67898745-7)', with a red arrow and the number '2' pointing to it, and a 'create new' button. Below this are links for 'Basics', 'License', 'Selections', and 'Invites'. A form contains several input fields: 'Name' (Nexe Test), 'VAT Id' (67898745-7), 'Street address' (Tekniikantie 11), 'Postal code' (021500), 'Postal area' (Espoo), 'Encryption key', and 'Prefix for username'. At the bottom are 'Save', 'Delete', and 'Reset' buttons.

1. Choose "Licenses" from the menu.

2. Choose the customer from the drop-down menu.



2. Adding extra space

Choose existing: <input type="text" value="NexeTest (67898745-7)"/> Or <input type="button" value="Create new"/>	
Basics License Connections Invites	
License	
<input type="button" value="Connect trial client"/>	
Number:	<input type="text" value="f3d95840-b00b-102e-8fc9-005056b36f47"/>
Type:	<input type="text" value="Purchased"/>
State:	<input type="text" value="Active"/>
Standard:	<input type="text" value="8"/> used 6
Server:	<input type="text" value="1"/> used 0
Extra space:	<input type="text" value="35"/> GB
Total Space:	<input type="text" value="125"/> GB
Client limit:	<input type="text" value="10"/> GB (0=not in use)
Created:	<input type="text" value="2011-04-04"/>
Valid to:	<input type="text" value="2012-04-03"/>
Comments:	<input type="text"/>
<input type="button" value="Save"/> <input type="button" value="Reset"/>	

1. Choose "License" from the submenu.

2. Insert the amount of extra space wanted, including the old extra space.

3. Lastly save.

	<p>The information will automatically be updated to the users.</p>
	<p>The Standard-license includes 5GB of disk space and the Server-license includes 50GB disk space.</p> <p>The program will automatically count the costumers disk space in the total space field. When you have entered the license amount and chosen save the total space will update itself.</p> <p><i>The disk space will be shared among the licenses. For example 5 standard licenses and one server license equals 75GB, however one workstation can have over 5GB backups as long as the total amount of all the licenses doesn't exceed 75GB</i></p>